

Crowd Linux 설치 가이드

이 문서는 Crowd 설치 가이드를 공유하기 위해 작성되었다.

OS	CentOS Linux 8
버전	4.4.4
비고	CentOS 7에서도 동일하게 설치 가능
비고	Mysql 8.0과 Crowd 연동

- [설치 환경](#)
- [Crowd 설치 파일 다운로드](#)
- [Crowd 압축 해제 및 설치 디렉토리 설정](#)
- [Crowd Home 디렉토리 설정](#)
- [Crowd 실행](#)
- [Crowd 설정](#)

설치 환경

- OS : CentOS Linux 8(x86-64)
- JAVA : openjdk version "1.8.0_312" (Crowd 설치 전 JAVA 설치가 필요하다.)
- Crowd : 4.4.4

Crowd 설치 파일 다운로드

아래 링크에 접속하여 최신 버전의 Crowd를 다운로드한다.

- <https://www.atlassian.com/ko/software/crowd/download-archive>

Crowd 압축 해제 및 설치 디렉토리 설정

Crowd 설치 파일 압축 해제 후 설치할 디렉토리로 복사 또는 이동

```
$ tar -xzf atlassian-crowd-4.4.4.tar.gz
$ mv atlassian-crowd-4.4.4 /app/atlassian
```

Crowd Home 디렉토리 설정

crowd-init.properties 파일 편집하여 Crowd home 경로 지정

```
$ vi /app/atlassian/atlassian-crowd-4.4.4/crowd-webapp/WEB-INF/classes/crowd-init.properties

#crowd.home=/var/crowd-home

crowd.home=/data/application-data/crowd-home
```

Crowd 실행

명령어를 이용해 Crowd 실행

```
$ /app/atlassian/atlassian-crowd-4.4.4/start_crowd.sh

$ cd /app/atlassian/atlassian-crowd-4.4.4
$ ./start_crowd.sh
```

실행 예시

```
[root@localhost ~]# /app/atlassian/atlassian-crowd-4.4.4/start_crowd.sh
To run Crowd in the foreground, start the server with /app/atlassian/atlassian-crowd-4.4.4/start_crowd.sh -fg
Using CATALINA_BASE:   /app/atlassian/atlassian-crowd-4.4.4/apache-tomcat
Using CATALINA_HOME:   /app/atlassian/atlassian-crowd-4.4.4/apache-tomcat
Using CATALINA_TMPDIR: /app/atlassian/atlassian-crowd-4.4.4/apache-tomcat/temp
Using JRE_HOME:        /usr
Using CLASSPATH:       /app/atlassian/atlassian-crowd-4.4.4/apache-tomcat/bin/bootstrap.jar:/app/atlassian
/atlassian-crowd-4.4.4/apache-tomcat/bin/tomcat-juli.jar
Using CATALINA_OPTS:
Using CATALINA_PID:   /app/atlassian/atlassian-crowd-4.4.4/apache-tomcat/work/catalina.pid
Tomcat started.
```

Crowd 설정

Crowd를 설정하기 위해 <http://localhost:8095> 으로 접속